

Proxmox VE root pass reset (break the glass)

If you forgot the password, it is possible to change password from the machine's console (physical access required):

Reset root password inside rescue shell:

Boot the server.

In GRUB menu press `e` to edit boot entry.

Find the linux kernel line starting with `linux`.

Add at the end:

```
init=/bin/bash
```

Boot with

```
CTRL+X
```

Remount filesystem read-write:

```
mount -o remount,rw /
```

Change password:



```
passwd
```

Reboot


```
reboot -f
```

Login with new pass, usually to port 8006


https://nn.nn.nn.nn:8006/



Change password (top-right, under username and 'Password')



Create admins user group



Create another admin user, add to admin user group created above

PROXMOX Virtual Environment 9.1.1

Server View

Datacenter

Search

Summary

Notes

Cluster

Ceph

Options

Storage

Backup

Replication

Permissions

Users

API Tokens

Two Factor

Groups

Pools

Roles

Realms

HA

SDN

Zones

VNets

Options

IPAM

VNet Firewall

Add Edit Remove Password Permissions Unlock TFA

User name ↑	Realm ↑	Enabled	Expire	Name	TFA	Groups
anton	pam	Yes	never		No	admins
root	pam	Yes	never		No	

Add: User

User name: anton First Name:

Realm: Linux PAM standard aut Last Name:

Group: admins E-Mail:

Expire: Group ↑ Comment Users

Enabled: admins

Comment:

Advanced Add

Define user's password

PROXMOX Virtual Environment 9.1.1

Server View

Datacenter

Search

Summary

Notes

Cluster

Ceph

Options

Storage

Backup

Replication

Permissions


Users

API Tokens

Add Edit Remove Password Permissions Unlock TFA

User name ↑	Realm ↑	Enabled	Expire	Name	TFA	Groups
anton	pam	Yes	never		No	admins
root	pam	Yes	never		No	

Add group permissions



Define permissions

Add: Group Permission ⊗

Path:

Group:

Role:

Propagate:

? Help Add

Revision #2

Created 13 June 2026 13:34:57 by Anton

Updated 13 June 2026 14:10:51 by Anton